



Inspec User Guide


ver.2020-MAR





User Administration

Role Management







		context
cacheAdmin	Cache Administrator	Access to: Cache Setup page under Maintenance Functions: Allows user to create, edit, and remove caches
bugAdmin	Bug Administrator	Access to: Bug Review Page Functions: Allows user to review and send bugs to Coolearth Software




Other Roles

Role Value	Role Name	Role Functions		
user (default)	User	Access to: Form pages Functions: Default role. Create and fill out forms		
GlobalStickyRole	Global Sticky Role	Access to: Form pages Functions: Allows user to save control values to be used again		
reopenFormsRole	Reopen Form Role	Access to: Form pages Functions: Allows users to reopen forms		
reopen1hr	Reopen forms roles	Access to: Form pages Functions: Allows user to reopen a form within 1 hour of finishing the form		





Windows Active Directory (A/D) User Authentication



Environment Settings:

- Idap_servername
- Idap_extended

How to Add, Setup and Configure Users


Role Permissions Needed

You need to login as a user who has been given the "Admin" role. Once in, open the Main Menu, and select Users under the Administrative section.






Add a User from the User Maintenance



You will see the Local User Maintenance screen.



To add a User:


Enter the information about the user at the top of the screen. Fill out the username, the user's full name, email,






and password, then press the Add/Edit User button.

After the user has been added, select the user in the list, and press the Modify User button. This will take you to that user's information page.
















Add a list of Users via the Import process








How to Configure a User

Set the user's context to be Icicle→Gordon Jensen (or whatever is valid for your user). To do this, go to the Context portion of the screen, drop-down the list, and select Gordon Jensen from the list.

In addition, you need to set the role to be "User". In the Roles & Role Groups section, select "User" from the dropdown, or type it in and press the Add Role button.

When you are finished, return to the User Maintenance screen by pressing the back arrow (\leftarrow) in the upper left hand corner of the browser window.




User Context Administration

If you have multiple users to add to the same context, then you can do all of them at the same time through the






Context Maintenance screen.



Select all the users in the list that you want to set, select the context from the dropdown, then press the Add Users To Context button to do all of the users at once.



Password Resetting


When the user wishes to reset their password they can do so as an administrator. A user can not reset a password if they do not have administrator privileges.





To reset a user's password,


Select the <Menu> slide-out from the top menu bar.




Select the <Users> option from the administrative drop-down.








The user will see a list of all users in the specific system. From here the administrator can select the user they wish to augment. By selecting <Reset Password> a dialog box will be presented to the administrator that will prompt the administrator to input the new password and select "OK" to authorize the new password.










Resetting a user's password will log them out of all sessions and require them to log into new sessions.

User Context Maintenance




The user context maintenance allows a user to add, remove, reset, and assign importance to contexts.

To get to the user context maintenance select the <Menu> slide-out. Select the <Administrative> drop-down and <Users>. Next, select the <Editing User Context Maintenance> tab, from the top submenu.



























Select the user that needs contexts added or subtracted from them, with the check box.



Select context to assign in the drop-down submenu.




next, select the function the user wishes to perform with the context. <Add Users to Context>, <Remove Users from Context>, <Primary Context>, <Reset to Default>.





- <Add Users to Context> will add the selected context to the selected user(s).
- <Remove Users from Context> will remove the selected context from the selected user(s).
- <Primary Context> will make the selected context the primary context of the selected user(s).
- <Reset to Default> will remove non-default contexts and replace them with default contexts.


Context actions.




Adding user(s) to a context.








Setting primary contexts.




Resetting to Default










User Enrollment Maintenance





Role Permissions Needed				
Role Value	Role Name			
userAdmin	User Administrator			

Group Management



Role Permissions Needed				
Role Value	Role Name			
cardAdmin	Card Administrator			
formAdmin	Form Administrator			
menuAdmin	Menu Administrator			
dataAdmin	Data Administrator			
deleteAdmin	Delete Administrator			

Other Roles:

- User (Default)
 - o reopen forms
- Global Sticky Role (Thumb-tack feature)






- Reopen Forms Role (make this a super-cede to the "reopen forms" role.)
- Approval Role (make this a super-cede to the "approver" role.)


See the "Security Window"


To get to the user context maintenance select the <Menu> slide-out. Select the <Administrative> drop-down and select <Security>.












Once in the groups screen, the user can select an existing group or create a new group.







Can see and access /qc/review (Form Review) window (to be placed in the Maintenance menu) (example: http://qcproduction.coolearth.com/qc/review)







Group Administration

How to Add a new Group and assign Roles and Users to a Group


To create a new group, select <Add New Group>



Enter a group name, and select <OK>.




To complete the group, add users to the group via the "Users" drop-down.











Then, add roles via the "Roles" to the chosen users.





Deleting and editing existing groups can also be completed in the group management screen. To delete existing groups, perform all the steps listed above to get to the group management screen and to access an existing group.






How to Edit a Group


Once in the groups screen, the user can select an existing group by selecting the name of the desired existing group.

Now the user will be brought to the group editing screen.



To edit the form name, users, or roles toggle the drop-down menu or edit the group name.


The figure shows the drop-down menus that allow the user to edit the users of the group and the roles assigned to those users.



This figure shows the field that the group's name will appear to be edited in. To edit the name, select the field, highlight the name and write over the existing name with the name desired.








How to Delete a Group


To delete the group select the trash can icon that appears in the editing screen.








Tasking Management





To get to the user context maintenance select the <Menu> slide-out. Select the <Administrative> drop-down and select <Tasking>.



















To create a task,

Select the task type with either <Recurring> or <Single> actions.


"Recurring" will make the task repetitive on a scale set by the user in the screen prompted after selecting "Recurring".




"Single" will make the task a one time only function that occurs when the user sets it to.








Next, Select who to assign the task to with either the <Person> or <Group> actions.




"Person" will present a "Person" drop-down menu that will prompt the user to select the name of a user for the task to be assigned to.








"Group" will present a drop-down menu for the user to choose the group to assign the task to. Selecting "group" will also populate a "Task Copy" button-bar, with the actions of <Shared Copy> or <Per User Copy>.




Selecting "Shared Copy" will create one task screen for every user in the group to work in.




Selecting "Per User Copy" will distribute a copy of the task to every user in the group to work on individually.








Select the form the user wishes to complete with the task, using the "form" drop-down.




Name the task in the "task name" field.








Select a start time with the "date and time" field.




Select an amount of time you with the form to be completed in, for the users.








Lasty, save the task to complete tasking.



UAT (User Acceptable Testing) Management









This functionality allows for the User to test a given Inspec build for acceptable use. By testing a set of common data collection forms, the user can note any odd or unexpected behavior while simulating data collection.

To get to the UAT testing page in Inspec, select the <Menu> slide-out. Select the <Administrative> drop-down and select <UAT>. Make sure the uatAdmin permission is enabled for the user attempting to access the UAT menu.




Select the <Start New Test> button, this will populate a list of the 10 most used forms for your installation.



After the list has been presented the user can begin to test each form, by selecting <Start Test>, and work through them to determine operability of the specific Inspec build being test.








Inside each form being tested, on the bottom menu a navigation for Pass/Fail is provided. If the form is up to desired operability select <Pass>, if not select <Fail>.







If <Fail> is selected, the UAT test list has an option to use the new Bug Reporting functionality for the failed form.



At the end of the list, the Tester can complete the UAT testing regime with the <Complete Test> button and conclude that UAT session.





Inspec User Guide	1
User Administration	2
Role Management	2
Admin Roles	2
Other Roles	3
Windows Active Directory (A/D) User Authentication	4
How to Add, Setup and Configure Users	4
Role Permissions Needed	4
Add a User from the User Maintenance	5
Add a list of Users via the Import process	8
How to Configure a User	9
User Context Administration	9
Password Resetting	10
User Context Maintenance	13
Role Permissions Needed	13
User Enrollment Maintenance	20
Role Permissions Needed	21
Group Management	21
Role Permissions Needed	21
Group Administration	25
How to Add a new Group and assign Roles and Users to a Group	25
How to Edit a Group	27
How to Delete a Group	28
Tasking Management	29
Role Permissions Needed	29
UAT (User Acceptable Testing) Management	36
Role Permissions Needed	36